Resetting the Barcode Scanner

These instructions will walk you through the steps needed to reset your TraCS scanner information. A reset will typically need to happen when the port of the scanner is changed or when TraCS freezes on the "Loading Monitoring DLLs....." phase of startup.

N:	10 M A.	
Traffic and	Criminal Software	
TraCS Traffic and Criminal Softwar	e	
Office 10.02.02.1 Copyright © 2010 Loading Monitoring DLLs		

1. Open the TraCS Configuration Manager. This can typically be found by first clicking on Start in the lower left corner of Windows. From there, select All Programs -> TraCS -> TraCS Configuration Manager.



2. Log in using proper credentials for TraCS Configuration Manager.

Ø	Traffic and C	riminal Softw	are		
TraCS	TraCS Conf	iguration Manag	ger Login		
Traffic and C	User ID:	00001			
	Password:	****			
			OK Cance	4	
Office	10.02.02.1				

3. Once open, open the Settings Editor by clicking on the Settings button.



4. On the list on the left side of the screen, expand HHPBarcodeReader4600.ini. To expand, click on the "+" button to the left of the label.



5. Expand Barcode the same way.



6. Click on ComPort. We will want to completely clear out any information stored in the ComPort text field on the right side of the screen. To do this, click in the ComPort text field and delete the text in the field.



ComPort
<u>C</u>]
Comments:

7. Click on DeviceName, located on the list to the left. Completely clear out any information stored in the DeviceName text box found on the right.

🗜 AutoNumber.ini	Values
🖶 Transmission.INI	
i ⊕- Settings.Ini	
- MachineID.Ini	
∯ Splash.Ini	DeviceName
- GPS.Ini	kooode Desember Deseder
HHPBarcodeReader4600.Ini	4800dr Document Reader
🖨BarCode	
ComPort	
BaudRate	
SavePictureQuality	Comments:
BarCodeInputWait	
ImageInputWait	
ImagerJPEGQuality	
- FirmwareVersion	
LightsOn	
- Exposure	Full File Dath
DeviceName	C: (Documents and Settings(All Users(Application Data) TraCS) Settings) DLL
Ð- TopazSignature.Ini	Settings\HHPBarcodeReader4600.Ini
Đ- ESD.Ini	
₽- QuickScene.Ini	
B- ScenePD.Ini	
pri (rausulagram,In)	
priserialbar LodeReader, Ini	
MACH TRACSPORT Di	
OK Cancel Apply	
Concor Hpply	
	Help

Device	Name		

8. Click on AllowAutoDetect, located on the list to the left. Pull down the drop down list to the right by clicking on the down pointing arrow. Select True.

- AutoNumber.ini	Values
- Transmission.INI	
- Settings.Ini	
MachineID.Ini	
Splash.Ini	AllowAutoDetect
- GPS.Ini	
- HHPBarcodeReader4600.Ini	False
🖨 BarCode	
ComPort	
BaudRate	
SavePictureQuality	Competer
BarCodeInputWait	Comments,
ImageInputWait	
ImagerJPEGQuality	
FirmwareVersion	
LightsOn	
Exposure	
AllowAutoDetect	
DeviceName	C:\Documents and Settings\All Users\Application
opazSignature.Ini	Settings/HHPBarcodeReader4600.Ini
ESD.Ini	
- QuickScene.Ini	
l ScenePD.Ini	
h-Visio.Ini	
- TraCSDiagram.Ini	
- SerialBarCodeReader.Ini	
- CodeCorpBarCodeReader.ini	
MACH_TraCSBot.Ini	
OK Cancel Apply	
	Liele
	nep

Values	
	AllowAutoDetect
	False +
	True
	False
	Comments:

9. Click OK and then Exit the TraCS Configuration Manager.



- 10. Open up TraCS and log in as yourself.
- 11. A pop up will appear during startup asking you to locate the barcode reader. A list of the available ComPorts will show up in this popup. You might see many different choices on your list. Typically, the barcode scanner will have a device name of 4800dr Document Reader. Please select the ComPort with that name. If you select something other than 4800dr, IT WILL NOT WORK. The scanner will sing after hitting Select if the ComPort selection was correct.

Locate Device - Barcode	e Reader			
COM1 - Communications P	Port Reader			
Remember Selection	Baud Rate 115200	Select	Cancel	Don't Use Barcode